

## INSTRUCTIONS FOR USING THE POLAROID SLIDEMAKER WITH POWERPOINT

1. Make sure the film is ISO 100 or ISO 200 for color slides.
2. Turn on the Polaroid slide maker and allow it to warm up for 15-20 minutes before using it.
3. Restart the computer so that the hardware is recognized. Select the Start menu, choose shut down, and then select restart.
4. Load the film -- just like you would in a regular photographic camera. After closing the back cover, the camera will automatically advance the film to the first frame. You can confirm that by looking at the film counter on the left edge of the camera body.
5. In PowerPoint, first go to the File menu and select "Page Setup". By default, PowerPoint sets the size of the slides to "Screen Show". When shooting slides, you should change that to "35 mm film". **CAUTION:** This change will alter the horizontal dimension of all your slides. **ALWAYS** go through your slides one more time before you start shooting the slides. The change in the horizontal dimension typically alters the position of any extra elements you added by hand (i.e., floating text labels on charts, freehand drawings, "auto-shapes", clipart etc).
6. Also from the Page Setup, make sure that the orientation setting **for slides** is set to "Landscape".
7. Click "OK".
8. Again from the File menu, select "Print..."
9. The selected printer should be "Digital Palette CI-5000". If the laser printer is selected instead, use the drop-down menu to select the "Digital Palette CI-5000".
10. Select the "Properties" button. From the "Paper" tab, select "PowerPoint 35 mm" for Paper Size (2nd from the left).

11. For Orientation, make sure that "Landscape" is selected.
12. Click on the "Device Options" tab. Use the "Change Setting for Film Type" menu to select either "Ekta Elite 100 v6" or "Ekta Elite 200 v6", depending on whether you are using film with ISO 100 or ISO 200, respectively.
13. Click "OK".
14. From the "Print" window, make sure that the "Print What" option shows: "Slides" and that "Black and White", "Scale to Fit Paper", "Pure Black and White", and "Frame Slides" boxes are **NOT** selected.
15. In the "Print Range" option, you can either select "All" if you wish to print all the slides in the presentation (assuming that your film has enough frames) or you can specify which slides to shoot. For example, by giving: 1-9,18,23-24  
In the "Slides:" box, PowerPoint will only print from slide 1 to slide 9, slide 18, and slides 23 and 24.
16. Click "OK". Expect that the procedure will take about 5 minutes per slide.